

RED HEART PRISMATIC CHROMATIC CROCHET BLANKET



**MATERIALS**

**Red Heart® Super Saver™** (7 oz/198 g; 364 yds/333 m)

<b>Contrast A</b> Black (0312)	<b>1 ball</b>
<b>Contrast B</b> Real Teal (0656)	<b>1 ball</b>
<b>Contrast C</b> Minty (0520)	<b>2 balls</b>
<b>Contrast D</b> Shocking Pink (0718)	<b>2 balls</b>
<b>Contrast E</b> Dark Orchid (0776)	<b>2 balls</b>
<b>Contrast F</b> Carrot (0256)	<b>2 balls</b>
<b>Contrast G</b> Gold (0321)	<b>1 ball</b>
<b>Contrast H</b> Aran (0313)	<b>2 balls</b>

Size U.S. H/8 (5 mm) crochet hook **or size needed to obtain gauge.**  
6" [15 cm] wide piece of cardboard for Tassels.



CROCHET | SKILL LEVEL: **EASY**

**ABBREVIATIONS**

**Approx** = Approximately  
**Beg** = Begin(ning)  
**Ch** = Chain(s)  
**Dc** = Double crochet  
**Rem** = Remain(ing)  
**Rep** = Repeat  
**Rnd(s)** = Round(s)

**Sl st** = Slip stitch  
**Sp(s)** = Space(s)  
**St(s)** = Stitch(es)  
**Tog** = Together  
**WS** = Wrong side  
**Yoh** = Yarn over hook

**MEASUREMENT**

Approx 61" [155 cm] square.

**GAUGE**

12 dc and 7 rows = 4" [10 cm].  
 Motif = 5" [12.5 cm] square.

**INSTRUCTIONS**

**Notes:**

- Ch 3 at beg of rnd counts as dc throughout.
- 2 colors are worked in each rnd.
- When changing colors, hold color not in use at WS of work.
- Motif is worked back and forth, then joined to form rnds.

**MOTIF**

Make 10 – A: Color 1 and B: Color 2.  
 Make 18 – B: Color 1 and C: Color 2.  
 Make 27 – C: Color 1 and D: Color 2.  
 Make 34 – D: Color 1 and E: Color 2.  
 Make 27 – E: Color 1 and F: Color 2.  
 Make 18 – F: Color 1 and G: Color 2.  
 Make 10 – G: Color 1 and H: Color 2.

With Color 1, ch 3. Join with sl st to first ch to form ring. See diagram on page 2.

**1st rnd:** (RS). Ch 3. (2 dc. Ch 2. 3 dc) in ring. Ch 1. Drop Color 1. With Color 2, ch 1. (3 dc. Ch 3. 3 dc) in ring. Ch 1. Join with hdc to top of beg ch-3. Turn.

**2nd rnd:** (WS). With Color 2, ch 3. 1 dc in beg sp created by ch-1 and hdc at end of last rnd (beg sp).

## RED HEART PRISMATIC CHROMATIC CROCHET BLANKET

\*1 dc in each dc to corner ch-2 sp. (2 dc. Ch 2. 2 dc) all in ch-2 sp. 1 dc in each dc to corner ch-2 sp.\* 2 dc in next ch-2 sp. Ch 1. Drop Color 2. With Color 1, ch 1. 2 dc in same ch-2 sp. Rep from \* to \* once more. 2 dc in beg sp. Ch 1. Join with hdc to top of beg ch-3. Turn.

**3rd rnd:** (RS). With Color 1, ch 3. 1 dc in beg sp. \*1 dc in each dc to corner ch-2 sp. (2 dc. Ch 2. 2 dc) all in ch-2 sp. 1 dc in each dc to corner ch-2 sp.\* 2 dc in ch-2 sp. Ch 1. Drop Color 1. With Color 2, ch 1. 2 dc in same ch-2 sp. Rep from \* to \* once more. 2 dc in beg sp. Ch 1. Join with hdc to top of beg ch-3. Turn.



**4th rnd:** As 2nd rnd. Fasten off.

Join Motifs tog as shown in Assembly Diagram.

**Border:** (RS). Join A with sl st to any corner ch-2 sp of Blanket. Ch 3. 1 dc in each dc or ch-2 sp around, working 5 dc in each corner of Blanket. Join with sl st to top of ch-3. Fasten off.


**Tassels** (make 4 with H)  
Cut a piece of cardboard 6" [15 cm] wide. Wind yarn around cardboard

120 times. Break yarn leaving a long end and thread end through needle. Slip needle through all loops and tie end tightly. Remove cardboard and wind yarn tightly around loops 1" [2.5 cm] below fold. Fasten securely. Cut through rem loops and trim ends evenly. Sew 1 Tassel to each corner of Blanket.



MOTIF

### Assembly Diagram



#### STITCH KEY

- = chain (ch)
- = slip stitch (sl st)
- ┆ = half double crochet (hdc)
- ┆ = double crochet (dc)
- ↔ = direction of work
- = color 1