Yarnspirations spark your inspiration!

BERNAT LONG DASH CROCHET TOP | CROCHET



MATERIALS

Bernat® Maker Fashion™ (3.5 oz/100 g; 126 yds/115 m)

 Sizes
 XS/S
 M
 L
 XL
 2/3XL
 4/5XL

 Gray (06008)
 7
 7
 8
 9
 11
 12

or 800 yds/730 m, 880 yds/800 m, 970 yds/885 m, 1070 yds/975 m, 1325 yds/1205 m, 1450 yds/1320 m

Size U.S. L/11 (8 mm) crochet hook **or size needed to obtain gauge**. 4 stitch markers.

ABBREVIATIONS:

Approx = Approximate(ly)

Beg = Begin(ning) **Ch** = Chain(s)

Cont = Continue(itv)

Dc = Double crochet

Dcbp = Yoh and draw up a loop around post of next stitch from back to front to back. (Yoh and draw

through 2 loops on hook) twice.

Dcfp = Yoh and draw up a loop around post of next stitch from front to back to front. (Yoh and draw through 2 loops on hook)

Hdc = Half double crochet

twice.

Pat = Pattern Rem = Remaining

balls

Rep = Repeat **RS** = Right side

SI st = Slip stitch

Sp = Space
St(s) = Stitch(es)

WS = Wrong side

Yoh = Yarn over hook

CROCHET | SKILL LEVEL: EASY

SIZES

To fit bust measurement

 Extra-Small/Small
 28-34" [71-86.5 cm]

 Medium
 36-38" [91.5-96.5 cm]

 Large
 40-42" [101.5-106.5 cm]

 Extra-Large
 44-46" [112-117 cm]

 2/3 X-Large
 48-54" [122-137 cm]

 4/5 X-Large
 56-62" [142-157.5 cm]

Finished bust

 Extra-Small/Small
 39" [99 cm]

 Medium
 41" [104 cm]

 Large
 45" [114.5 cm]

 Extra-Large
 50" [127 cm]

 2/3 X-Large
 56" [142 cm]

 4/5 X-Large
 63" [160 cm]

GAUGE:

10 sts and 7.5 rows = 4" [10 cm] in Dash Pat.

INSTRUCTIONS

The instructions are written for smallest size. If changes are necessary for larger size(s) the instructions will be written thus (). Numbers for each size are shown in the same color throughout the pattern. When only one number is given in black, it applies to all sizes.

BACK

Ch **51 (**53-59-65-73-81**).

Foundation row: (WS). 1 dc in 4th ch from hook (counts as 2 dc). 1 dc in each ch to end of chain. Turn. **49** (51-57-63-71-79) dc.

Note: Ch 2 at beg of row does not count as hdc.

Proceed in Dash Pat as follows:

1st row: (RS). Ch 2. 1 hdc in first st. *Dcfp around post of next st. 1 hdc in next st. Rep from * to end of row. Turn.

2nd row: Ch 2. 1 hdc in first st. *Dcbp around post of next st. 1 hdc in next st. Rep from * to end of row. Turn.

3rd row: Ch 2. 1 hdc in each of first 2 sts. *Dcfp around post of next st. 1 hdc in next st. Rep from * to last st. 1 hdc in last st. Turn.

4th row: Ch 2. 1 hdc in each of first 2 sts. *Dcbp around post of next st. 1 hdc in next st. Rep from * to last st. 1 hdc in last st. Turn.

These 4 rows form Dash Pat.**

Cont in pat until work from beg measures approx **22** (22-23-23-24-24)" [56 (56-58.5-58.5-61-61 cm], ending on a WS row.



BERNAT LONG DASH CROCHET TOP | CROCHET

Shape neck: Next row: (RS). Ch 2. Pat across **14** (**15-17-19-23-27**) sts (neck edge). **Turn.** Leave rem sts unworked. Work 1 row even in pat. Fasten off.

With RS facing, skip center 21 (21-23-25-25-25) sts. Rejoin yarn with sl st to next st. Ch 2. 1 hdc in same sp as last sl st. Pat to end of row. Turn.

Work 1 row even in pat. Fasten off.

FRONT

Work from ** to ** as given for Back.
Cont in pat until work from beg measures
6 rows less than Back to shoulder, ending
on a WS row.

Shape neck: Next row: (RS). Ch 2. Pat across **14** (**15-17-19-23-27**) sts (neck edge). **Turn.** Leave rem sts unworked. Work 5 rows even in pat. Fasten off.

With RS facing, skip center 21 (21-23-25-25-25) sts. Rejoin yarn with sl st to next st. Ch 2. 1 hdc in same sp as last sl st. Pat to end of row. Turn.

Work 5 rows even in pat. Fasten off.

FINISHING

Block all pieces to measurements. Cover with a damp cloth leaving cloth to dry. Sew shoulder seams.

Place markers on side edges 11 (11-12-12-13-13)" [28 (28-30.5-30.5-33-33) cm] down from shoulder seams and 5" [12.5 cm] up from lower edge. Sew side seam between markers, leaving deep armholes open and creating side slits.

